






Restoring HDD image




To run MAN CATS software you will need:

- PC with hard drive at least of **40Gb**
- Free **PCMCIA** slot.




1. Put DVD to the DVD ROM, then boot PC from it.
2. Run Acronis and restore TIB file from this DVD to the hard disk. **WARNING: ALL DATA ON YOUR HARD DRIVE WILL BE DELETED!!!**









During restore please **select Universal Restore**, otherwise after restore PC will not boot!






On systems with SATA hard drive at the end of restore window asking to install drivers appears, point it to *SATADrivers* folder on DVD.

Setting up system drivers


3. To make changes to the system you should log on as MCDevTeam user, no password is required. **If MAN CATS software is already running, log off and logon as MCDevTeam, or during Windows booting hold on Shift key pressed.**




- 3.1. Logon as MCDevTeam user, install all missed drivers for your particular PC. Reboot PC if required.
- 3.2. Insert wireless card from the set to free PCMCIA slot




in Device manager go to "Network adapters"




you should see




"Symbol Spectrum24 WLAN PC Card" with yellow exclamation mark or "Symbol Spectrum23 WLAN PC Card". Right click on it, select "Update Driver..."




select "Install from a list or specific location (Advanced)"





then "Don't search, I will choose the driver to install."



then select "Symbol LA302x Spectrum24 Wireless LAN PCMCIA Card"






answer **"Continue Anyway"**




When missed file dialog appears point it to folder Spectrum24 on the desktop.

When "Spectrum24 Easy Setup" dialog appears just press Ok.




Press **Finish**, skip warning message, reboot your PC.



After reboot yellow exclamation mark for "Symbol LA302x Spectrum24 Wireless LAN PCMCIA Card" in Device manager should go off.


To finish wireless card setup, set IP address 192.168.0.1, subnet mask 255.255.255.0 for Wireless Network Connection.



- 3.3. To make cable connection to diagnostic interface working, set IP address 192.168.1.2, subnet mask 255.255.255.0 for Local Area Connection.
- 3.4. Reboot your PC. Now you can work with your diagnostic interface.
4. Remove DVD then reboot your PC, Windows XP should boot, MAN CATS software will run automatically.

Setting up MAN CATS software

You MUST enter MAC address of your interface (back labelled on device) in the software, otherwise link will not work!



1. Reboot your PC, MAN CATS software will run automatically. Press System icon from the right upper corner.
2. Go to "System settings", then "Interface settings". Select "Configure interface" from the right panel.
3. Enter MAC address of your device as it is labelled on its back side. Confirm it, then follow instructions to establish link to the interface.

If you want to connect diagnostic interface via Ethernet cable, you should change interface to "Cable interface CCI". To switch back to wireless connection, select "Radio interface WCI".

Misc notes

Windows password for MANcats user is MANCATS